

Dialplans

Dialplan Application

Dialplan Application uses FreeSWITCH **show application** to build the dropdown lists that are found in FusionPBX dialplans. This is a list from a default install and the list can change depending on how many FreeSWITCH modules are installed.

name	description	syntax	ikey	
answer	Answer the call		mod_dptools	
att_xfer	Attended Transfer		mod_dptools	
bgsystem	Execute a system command in the background		mod_dptools	
bind_digit_action	bind a key sequence or regex to an action	,<digits ~regex>,[,] [,][,]	mod_dptools	
bind_meta_app	Bind a key to an application	[a b ab] [a b o s i 1]	mod_dptools	
block_dtmf	Block DTMF		mod_dptools	
break	Break		mod_dptools	
bridge	Bridge Audio		mod_dptools	
bridge_export	Export a channel variable across a bridge	=	mod_dptools	
callcenter	CallCenter	queue_name	mod_callcenter	
capture	capture data into a var		mod_dptools	
check_acl	Check an ip against an ACL list	[]	mod_dptools	
clear_digit_action	clear all digit bindings	all[,target]	mod_dptools	
clear_speech_cache	Clear Speech Handle Cache		mod_dptools	
cng_plc	Do PLC on CNG frames		mod_dptools	
conference	conference		mod_conference	
conference_set_auto_outcall	conference_set_auto_outcall		mod_conference	
db	Insert to the db	[insert delete]///	mod_db	
decode_video	decode picture	[max_pictures]	mod_fsv	
deduplicate_dtmf	Prevent duplicate inband + 2833 dtmf	[only_rtp]	mod_dptools	
deflect	Send call deflect		mod_dptools	
delay_echo	echo audio at a specified delay		mod_dptools	
detect_audio	detect audio	[]	mod_dptools	
detect_silence	detect silence	[]	mod_dptools	
detect_speech	Detect speech	[] OR grammar [] OR nogrammar OR grammaron/gramm aroff OR grammarsalloff	mod_dptools	
		OR pause OR resume OR start_input_timers OR stop OR param		
digit_action_set_realm	change binding realm	[,]	mod_dptools	
displace_session	Displace File	[] [+time_limit_ms]	mod_dptools	
early_hangup	Enable early hangup		mod_dptools	

Dialplans

name	description	syntax	ikey	
eavesdrop	eavesdrop on a uuid	[all]	mod_dptools	
echo	Echo		mod_dptools	
enable_heartbeat	Enable Media Heartbeat	[0]	mod_dptools	
enable_keepalive	Enable Keepalive	[0]	mod_dptools	
endless_playback	Playback File Endlessly		mod_dptools	
enum	Perform an ENUM lookup	[reload []]	mod_enum	
eval	Do Nothing		mod_dptools	
event	Fire an event		mod_dptools	
execute_extension	Execute an extension		mod_dptools	
export	Export a channel variable across a bridge	=	mod_dptools	
fax_detect	Detect faxes		mod_dptools	
fifo	Park with FIFO	[!] [in [undef] [undef] out [wait nowait] [undef] [undef]]]	mod_fifo	
fifo_track_call	Count a call as a fifo call in the manual_calls queue		mod_fifo	
fire	fire the message		mod_sms	
flush_dtmf	flush any queued dtmf		mod_dptools	
gentones	Generate Tones	[I]	mod_dptools	
group	Manage a group	[insert delete]::	mod_db	
hangup	Hangup the call	[]	mod_dptools	
hash	Insert into the hashtable	[insert insert_ifempty delete delete_ifmatch]///	mod_hash	
hold	Send a hold message	[]	mod_dptools	
info	Display Call Info		mod_sms	
info	Display Call Info		mod_dptools	
intercept	intercept	[-bleg]	mod_dptools	
ivr	Run an ivr menu		mod_dptools	
jitterbuffer	Send session jitterbuffer		mod_dptools	
limit	Limit	[[/interval]] [number [dialplan [context]]]]	mod_dptools	
limit_execute	Limit	[/interval] [application arguments]	mod_dptools	
limit_hash	Limit	[[/interval]] [number [dialplan [context]]]]	mod_dptools	
limit_hash_execute	Limit	[/interval] [application arguments]	mod_dptools	
log	Logs to the logger		mod_dptools	
loop_playback	Playback File looply	[+loops]	mod_dptools	
media_reset	Reset all bypass/proxy media		mod_dptools	

Dialplans

name	description	syntax	ikey	
	flags			
mkdir	Create a directory		mod_dptools	
multiset	Set many channel variables	[^^]= =	mod_dptools	
multiunset	Unset many channel variables	[^^]	mod_dptools	
mutex	block on a call flow only allowing one at a time	[on off]	mod_dptools	
novideo	Refuse Inbound Video		mod_dptools	
park	Park		mod_dptools	
park_state	Park State		mod_dptools	
phrase	Say a Phrase	,	mod_dptools	
pickup	Pickup	[]	mod_dptools	
play_and_detect_speech	Play and do speech recognition	detect: {param1=val1,param2=val2}	mod_dptools	
play_and_get_digits	Play and get Digits	[] ['failure_dp [failure_context]]']	mod_dptools	
play_fsv	play a fsv file		mod_fsv	
play_yuv	play a yuv file	[width] [height]	mod_fsv	
playback	Playback File		mod_dptools	
pre_answer	Pre-Answer the call		mod_dptools	
preprocess	pre-process		mod_dptools	
presence	Send Presence	[]	mod_dptools	
privacy	Set privacy on calls	off on name full number	mod_dptools	
push	Set a channel variable	=	mod_dptools	
queue_dtmf	Queue dtmf to be sent		mod_dptools	
read	Read Digits		mod_dptools	
record	Record File	[] [] []	mod_dptools	
record_fsv	record an fsv file		mod_fsv	
record_session	Record Session	[+]	mod_dptools	
record_session_mask	Mask audio in recording		mod_dptools	
record_session_unmask	Resume recording		mod_dptools	
ask				
recovery_refresh	Send call recovery refresh		mod_dptools	
redirect	Send session redirect		mod_dptools	
remove_bugs	Remove media bugs	[]	mod_dptools	
rename	Rename file		mod_dptools	
reply	reply to a message		mod_sms	
respond	Send session respond		mod_dptools	
ring_ready	Indicate Ring_Ready		mod_dptools	
rxfax	FAX Receive Application		mod_spandsp	
say	say	[:] []	mod_dptools	
sched_broadcast	Schedule a broadcast in the future	[+] [aleg bleg both]	mod_dptools	
sched_cancel	cancel scheduled	[group]	mod_dptools	

Dialplans

name	description	syntax	ikey	
	tasks			
sched_hangup	Schedule a hangup in the future	[+] []	mod_dptools	
sched_heartbeat	Enable Scheduled Heartbeat	[0]	mod_dptools	
sched_transfer	Schedule a transfer in the future	[+]	mod_dptools	
send	send the message as-is		mod_sms	
send_display	Send session a new display		mod_dptools	
send_dtmf	Send dtmf to be sent		mod_dptools	
send_info	Send info		mod_dptools	
session_loglevel	session_loglevel		mod_dptools	
set	set a variable		mod_sms	
set	Set a channel variable	=	mod_dptools	
set_audio_level	set volume		mod_dptools	
set_global	Set a global variable	=	mod_dptools	
set_media_stats	Set Media Stats		mod_dptools	
set_mute	set mute		mod_dptools	
set_name	Name the channel		mod_dptools	
set_profile_var	Set a caller profile variable	=	mod_dptools	
set_user	Set a User	@ [prefix]	mod_dptools	
set_zombie_exec	Enable Zombie Execution		mod_dptools	
sleep	Pause a channel		mod_dptools	
socket	Connect to a socket	[:]	mod_event_socket	
sofia_sla	private sofia sla function		mod_sofia	
soft_hold	Put a bridged channel on hold	[] []	mod_dptools	
sound_test	Analyze Audio		mod_dptools	
spandsp_detect_tdd	Detect TDD data		mod_spandsp	
spandsp_inject_tdd	Send TDD data		mod_spandsp	
spandsp_send_tdd	Send TDD data		mod_spandsp	
spandsp_start_dtmf	Detect dtmf		mod_spandsp	
spandsp_start_fax_detect	start fax detect	[][][]	mod_spandsp	
spandsp_start_tone_detect	Start background tone detection with cadence		mod_spandsp	
spandsp_stop_detect_tdd	stop sending tdd		mod_spandsp	
spandsp_stop_dtmf	stop inband dtmf		mod_spandsp	
spandsp_stop_fax_detect	stop fax detect		mod_spandsp	
spandsp_stop_inject_tdd	stop sending tdd		mod_spandsp	
spandsp_stop_tone_detect	Stop background tone detection with cadence		mod_spandsp	
speak	Speak text		mod_dptools	
start_dtmf	Detect dtmf		mod_dptools	
start_dtmf_generate	Generate dtmf		mod_dptools	

Dialplans

name	description	syntax	ikey	
e				
stop	stop execution		mod_sms	
stop	Do Nothing		mod_dptools	
stop_displace_session	Stop Displace File		mod_dptools	
stop_dtmf	stop inband dtmf		mod_dptools	
stop_dtmf_generate	stop inband dtmf generation	[write]	mod_dptools	
stop_record_session	Stop Record Session		mod_dptools	
stop_tone_detect	stop detecting tones		mod_dptools	
stop_video_write_overlay	Stop video write overlay		mod_dptools	
stopfax	Stop FAX Application		mod_spandsp	
strftime	strftime	[]()	mod_dptools	
system	execute a system command		mod_sms	
system	Execute a system command		mod_dptools	
t38_gateway	Convert to T38 Gateway if tones are heard		mod_spandsp	
three_way	three way call with a uuid		mod_dptools	
tone_detect	Detect tones		mod_dptools	
transfer	Transfer a channel	[]	mod_dptools	
transfer_vars	Transfer variables	<~variable_prefix variable>	mod_dptools	
txfax	FAX Transmit Application		mod_spandsp	
unbind_meta_app	Unbind a key from an application	[]()	mod_dptools	
unblock_dtmf	Stop blocking DTMF		mod_dptools	
unhold	Send a un-hold message		mod_dptools	
unloop	Tell loopback to unfold		mod_loopback	
unset	unset a variable		mod_sms	
unset	Unset a channel variable		mod_dptools	
unshift	Set a channel variable	=	mod_dptools	
valet_park	valet_park	[[ask [] [] [] []] auto [in out] [min] [max]]	mod_valet_parking	
verbose_events	Make ALL Events verbose.		mod_dptools	
video_decode	Set video decode.	[[on wait] off]	mod_dptools	
video_refresh	Send video refresh.	[manual auto]	mod_dptools	
video_write_overlay	Video write overlay	[]()	mod_dptools	
wait_for_answer	Wait for call to be answered		mod_dptools	
wait_for_silence	wait_for_silence	[]()	mod_dptools	

Dialplans

Unieke FAQ ID: #4001

Auteur: Helpdesk

Laatst bijgewerkt:2022-11-28 09:33