

Applications

Conference Profiles

A group of conference parameters saved together as a profile.

Conference Profiles

SEARCH

A group of conference parameters saved together as a profile.

Name	Enabled	Description		
default	true			
wait-mod	true			
wideband	true			
ultrawideband	true			
cdquality	true			
sla	true			
page	true			
				

- Click the edit icon on the right to adjust the profile
- Click the plus to create a new profile

Default Profile

Applications

Conference Profile

BACK SAVE

Name	default
Enter the profile name.	
Enabled	<input checked="" type="checkbox" value="True"/>
Set the status of the profile.	
Description	
Enter the description.	

SAVE

Settings assigned to the conference profiles.

Name	Value	Enabled	Description	
cdr-log-dir	auto	true		 
domain		true		 
rate	8000	true		 
interval	20	true		 
energy-level	15	true		 
auto-gain-level	0	true		 
caller-controls	default	true		 
moderator-controls	moderator	true		 
muted-sound	conference/conf-muted.wav	true		 
unmuted-sound	conference/conf-unmuted.wav	true		 
alone-sound	conference/conf-alone.wav	true		 
moh-sound	local_stream://default	true		 
enter-sound	tone_stream://%(200,0,500,600,700)	true		 
exit-sound	tone_stream://%(500,0,300,200,100,50,25)	true		 
kicked-sound	conference/conf-kicked.wav	true		 
locked-sound	conference/conf-locked.wav	true		 
is-locked-sound	conference/conf-is-locked.wav	true		 
is-unlocked-sound	conference/conf-is-unlocked.wav	true		 
pin-sound	conference/conf-pin.wav	true		 
bad-pin-sound	conference/conf-bad-pin.wav	true		 
caller-id-name		true		 
caller-id-number		true		 
comfort-noise	true	true		 

+

- cdr-log-dir: Set as auto. Could be set manually and is enabled.
- domain: enabled.
- rate: The rate in kHz. 8000kHz and is enabled.
- interval: 20 is the default.
- energy-level: 15 is the default.
- auto-gain-level: 0 is the default.
- caller-controls: default is the default.
- moderator-controls: moderator is the default.
- muted-sound: conference/conf-muted.wav is the default.
- unmuted-sound: conference/conf-unmuted.wav is the default.
- alone-sound: conference/conf-alone.wav is the default.
- moh-sound: local_stream://default is the default.
- enter-sound: tone_stream://%(200,0,500,600,700) is the default.
- exit-sound: tone_stream://%(500,0,300,200,100,50,25) is the default.
- kicked-sound: conference/conf-kicked.wav is the default.
- locked-sound: conference/conf-locked.wav is the default.
- is-locked-sound: conference/conf-is-locked.wav is the default.
- is-unlocked-sound: conference/conf-is-unlocked.wav is the default.
- pin-sound: conference/conf-pin.wav is the default.
- bad-pin-sound: conference/conf-bad-pin.wav is the default.
- caller-id-name:
- caller-id-number:
- comfort-noise: true is the default.

Applications

Unieke FAQ ID: #4016

Auteur: Helpdesk

Laatst bijgewerkt: 2022-10-31 01:13